

Manual

1 Installation

MD2D needs the dependencies:

numpy
scipy
matplotlib
mdanalysis

It can be installed locally. Under the package directory.

```
> pip install .
```

Besides, MD2D and its required dependencies can be installed using pip:

```
> pip install md2d
```

2 Files

Input:

MD2D reads the output of molecular dynamics simulations in the VASP format. Only two input files will be read: XDATCAR and OUTCAR.

XDATCAR: MD2D reads in the trajectory from XDATCAR.

OUTCAR: MD2D reads in the following lines from OUTCAR:

- *POTIM = 1.0000 time-step for ionic-motion*
- *NBLOCK = 1; KBLOCK = 1 inner block; outer block*
- *Mass of Ions in am*
POMASS = 55.85
- *volume of cell : 711.71*
- *kin. lattice EKIN_LAT= 93.098925 (temperature 7275.16 K)*
- *Total+kin. 3416.08 3605.40 3585.13 -42.72 -109.39 -38.68*



The key words “*POTIM*”, “*NBLOCK*”, “*Mass of Ions in am*”, “*number of ions*”, “*volume of cell*”, “*EKIN_LAT=*”, “*Total+kin.*” are used for searching.

Besides, MD2D uses MDAnalysis to transform the outputs from other molecular dynamics codes to the VASP format. After installation, use the “md2vasp” command to initiate the conversion, or call the “md2v” function.

```
(py4vasp) yunguo@Lis-MacBook-Pro Fe100H10 % md2vasp

Please provide MD files to be loaded to MDAnalysis.
Example: ifabp_water.psf ifabp_water_0.pdb rmsfit_ifabp_water_1.dcd
For more info about MDAnalysis, please visit www.mdanalysis.org

Input your file names:
xdat.xyz

Files will be converted to XDATCAR_converted and OUTCAR_converted

/Users/yunguo/anaconda3/envs/py4vasp/lib/python3.10/site-packages/MDAnalysis/coordinates/
base.py:903: UserWarning: Reader has no dt information, set to 1.0 ps
warnings.warn("Reader has no dt information, set to 1.0 ps")
>>> No unitcell info provided <<<
Unitcell vectors will be:
(in Angstrom)
a-vector: 9.527216 0.000000 0.000000
b-vector: 0.000000 9.467003 0.000000
c-vector: 0.000000 0.000000 9.500980
Agreed? (y/n)y
Timestep will be 1.000000 ps
Agreed? (y/n)y

Python 3.10.2 | packaged by conda-forge | (main, Mar 8 2022, 16:02:23) [Clang 11.1.0 ] o
n darwin
Type "help", "copyright", "credits" or "license" for more information.
>>> import md2d
>>> md2d.md2v()

twine upload dist/*

Please provide MD files to be loaded to MDAnalysis.
Example: ifabp_water.psf ifabp_water_0.pdb rmsfit_ifabp_water_1.dcd
For more info about MDAnalysis, please visit www.mdanalysis.org
credentials you need to register to PyPI earlier.
Input your file names:
```

Output:

Calculated diffusion coefficients, viscosities, and correction to diffusion coefficient are streamed in standard output. Besides, $D\text{-}\tau$, mean squared displacement (MSD) and stress auto-correlation function (SACF) will be written into file as $X_D_tau.dat$ (X is the element name), $msd.dat$ and $sacf_average.dat$, and their plots are saved as $D_tau.pdf$, $msd.pdf$ and $SACF.pdf$. In each $X_D_tau.dat$, the first column is the time interval, the left three columns are the D s for x , y and z directions. The columns in $msd.dat$



corresponds to the MSDs for the elements in the order provided in XDATCAR. The three columns in `sacf_average.dat` are the MD step, bulk SACF and shear SACF.

3 How-To Guides

3.1 Launch the code

Simply import the package within python, and enter the menu by typing:

```
> import md2d
```

```
> md2d.diffusion(xdatcar="XDATCAR", outcar="OUTCAR")
```

It takes two variables: the names of input files. Default values will be XDATCAR and OUTCAR.

```
Python 3.10.2 | packaged by conda-forge | (main, Mar 8 2022, 16:02:23) [Clang 11.1.0] on darwin
Type "help", "copyright", "credits" or "license()" for more
>>> import md2d
>>> md2d.diffusion("XDATCAR", "OUTCAR")

      \
     / \
    /   \
   /     \
  /       \
 /         \
/           \
\           /
 \         /
  \       /
   \     /
    \   /
     \ /
      \

version 1.2.0 @ USTC

-----
--> 1) Diffusion coefficient (D)
--> 2) Viscosities and correction to D
--> 3) Mean squared displacement plot
--> 4) D- $\tau$  plot
--> 5) Stress auto-correlation function plot
--> 6) Quit

-----
Your option: 1
```

3.2 Calculate diffusion coefficient

Choose option 1 will lead to the calculation of diffusion coefficient. Then, MD2D will exhaust the available time intervals to calculate the diffusion coefficient as a function of time interval. The procedure and results will be streamed on the screen, and the $D-\tau$ data will be written into the file `X D tau.dat`.

Two integer parameters will be asked for, namely, the number of initial MD steps to drop and the number of MD steps to skip for each segment. The first is to drop out the unwanted/unequilibrated initial stage of MD. The second is to exclude the ballistic



motion stage from fitting the Einstein relation. The second parameter can be determined from the log-log plot or MSD.

```

--> 1) Diffusion coefficient (D)
--> 2) Viscosities and correction to D
--> 3) Mean squared displacement plot
--> 4) D-τ plot
--> 5) Stress auto-correlation function plot
--> 6) Quit
-----
Your option:1
Calculating diffusion coefficient .....
Initial MD steps to drop from the whole MD run:0
MD steps to skip for each segment:200

Segment length = 3333
D of Fe in direction X = 5.016428791076928e-09 +/- 5.58180035305796e-10 m^2/s
D of Fe in direction Y = 4.043024323646558e-09 +/- 2.932436645741134e-10 m^2/s
D of Fe in direction Z = 4.406197954027999e-09 +/- 1.036515311445878e-10 m^2/s
Averaged D of Fe = 4.4885503562504955e-09 +/- 3.1835841034149906e-10 m^2/s

Interval (fs) = 5000.0

Number of segments = 2
Segment length = 5000


D of Fe in direction X = 3.2981470135906934e-09 +/- 4.630220953012675e-10 m^2/s
D of Fe in direction Y = 3.896626536355361e-09 +/- 3.294874461732654e-10 m^2/s
D of Fe in direction Z = 4.255255969661351e-09 +/- 3.796677260716432e-10 m^2/s
Averaged D of Fe = 3.816676506535802e-09 +/- 3.907257558487254e-10 m^2/s

```

3.3 Plot D-τ

If diffusion coefficients have been calculated by doing option 1, then choose the option 4 will plot the D-τ curve.





If step one hasn't been done, they a warning message will prompt to do option 1 firstly.


```

-----
Your option:4
>>> This cannot be done. Step 1 needs to be done firstly. <<<
  
```

3.4 Calculate MSD

The MSD can be calculated and plotted by choosing option 3. The plot usually sees a change of trending, and the length of the first part is the length of ballistic motion that needs to be removed from fitting the Einstein relation.





3.5 Calculate viscosities and correction to diffusion coefficient

The stress auto-correlation function, viscosities, and correction to diffusion coefficient will be calculated by choosing option 2. The results will be streamed on the screen.

The correction to diffusion coefficient is best applied to single-component system, e.g., pure Fe liquid or molecular liquid. For complex system like silicate melt, an element- or component-wise correction according to Eq. (4) in Li and Ni, (2022) should be considered.




```
Your option:2
Calculating viscosities .....
Reading stresses from OUTCAR .....
Calculating stress auto-correlation function .....
Calculating viscosity from stress auto-correlation function .....
single-component system, e.g.,
Calculated bulk and shear viscosities are:
0.0046357311181300966, 0.012556958898286735 (Pascal*Second)
[ Ni, (2022) should be
Their uncertainties are:
0.002400124549182609, 0.0011427835182706988 (Pascal*Second)


Calculated correction to D is:
1.6695706485186846e-09 +/- 1.4037282864630724e-10 (m^2/s)
```

version 1.2.0 @ USTC

3.6 Plot stress auto-correlation function

The stress auto-correlation function can be plotted by choosing option 5 after finishing the calculation in option 2. Otherwise, MD2D will ask for doing option 2 firstly.





```
Your option:5
>>> This cannot be done. Step 2 needs to be done firstly. <<<
```

4 License & disclaimer

MD2D Copyright (C) University of Science and Technology of China. This file is part of MD2D.

MD2D is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation version 3 of the License.

MD2D is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with MD2D. If not, see <http://www.gnu.org/licenses/>.

